

E2EE - Installation

- Prerequisites
 - Community
 - Enterprise
- Installation
 - Demo License Key
- Download
- Manual Installation
- Administration Setup
- FAQ
 - I got a valid license, but when installing it, I still get a message that the system is unlicensed.
 - Are there any file size limitations?
 - How long do you have to wait to have a file de-/encrypted?

Prerequisites

You need access to the server running ownCloud in order to install the E2EE app.

- ownCloud 10 Installation with following optional apps installed:
 - **Activity:** <https://marketplace.owncloud.com/apps/activity> - to be able to view E2EE related events in the activity log
 - **Guests:** <https://marketplace.owncloud.com/apps/guests> >= 0.5 - to be able to share with guests by email address, i.e. users that do not have an account on the ownCloud Server


Community

Unfortunately, the market place can install e2ee directly only with an active enterprise license. But you can download the latest version from <https://marketplace.owncloud.com/apps/e2eeshare> and install it manually in apps-external or apps:

```
# Download to ~/Downloads, then (as root) do:
cd /var/www/owncloud/apps-external
tar -xzf ~/Downloads/e2eeshare-*.tgz
```

Enterprise

To enable/install these go to:

	You will find the guest app unter "Collaboration"	And the activity app can be found under "tools"
---	--	--

Versioning (files_versions) does not work with e2ee files. Unencrypted files are still supported.

Installation

You can find the newest E2ee release in the market place:



If you have problems using the marketplace app, you can also download the version from <https://marketplace.owncloud.com/apps/e2eeshare> and install it manually.

Demo License Key

You can test E2ee using `http(s)://localhost` or `http(s)://localhost/owncloud` for up to 10 users. If you need any other domains for testing, please contact sales@epikshare.com with the exact URL you want to test with.

```

-----BEGIN  LICENSE-----
TG1jMTtVZDNtcTQxSEx6VlpvaGNVUVhwckN20TJudytySERMYkVweFJFZ2FtcTZZWutuS3JBMj
V0
Z0FPaTZucTV4VzQ3Y0tMZZIrZ1QrbGZhZG9nZUZPcldMU2pTTVExV2RTM1RKK0tmb0NjSnNTZH
hR
UZZFQ1NnS0pypcnYrOHhhRDNDfPwWHV3U0EwUmg4TjNsRHN0bzNmbXBhMjg3ZH1sb1ZVTWRxby
t1
cEhaZnhZKy9aRTR00UtJdE8wRVVabk1xM2VGSm1NZDR6cnNBMy9KdzhCY1I5RHAWSFZudDFzQV
o4
SWBY1FiamR0a3RZUnpuS0R2bVc4RkVQZXJqdmx0VWU5Qmo3e1RXSFhXYkxmRFFNR2h0ZGZ3bz
Yx
aEprMnFxUWZZV3B2NXkwTGx1Qkd4RzI5MDR6VzhSVDhYT2NrZE1UQ0JlamlJnYwtYcGpUMEZZVD
A2
bFBQRxc9PTtkVDB5TURJMU1EWXpNRHRrUFdoMGRIQnpPaTh2Ykc5a1lXeG9iM04wSTJoMGRIQT
ZM
eTlzYjJ0aGJHaHZjM1FqYUhSMGNITTZMeTlzYjJ0aGJHaHZjM1F2YjNkdVkyeHZkV1FqYUhSMG
NE
b3ZMMnh2WTJGc2FH0XpkQz12ZDI1amJHOTFaQ05vZEhSd2N6b3ZMekV5Tnk0d0xqQXVNU05vZE
hS
d09p0HZNVEkzTGpBdU1DNHhPMmc5T0daaFpqTmhPV1ppWVRkbE16TXpPV05tTnpGak1UUTFNRE
Jr
TURRM09EZzFORGM1WXpKbE5EdGpQVEV3TzJVNztGeFJCZW1zSy8zYWZENnNjTXRzU25GRVNCcV
k9
-----END  LICENSE-----

```

Download

Download the latest e2eeshare version from <https://marketplace.owncloud.com/apps/e2eeshare>

If you have ownCloud enterprise you can use the marketplace to install the current version of e2ee-share.

Manual Installation

1. Find you apps folder within your ownCloud installation (Linux: /var/www/owncloud/apps-external)
2. Unzip the e2eeShare package into this folder:

```

cd /var/www/owncloud/apps-external
tar -xzf ~/Downloads/e2eeshare-*.tgz

```

3. Verify that the zip is successfully extracted:

```
owncloud
  apps-external
  ...
  e2eeshare
  |   |   ajax
      appinfo
      controller
      css
      db
      img
      js
      l10n
      lib
      templates
  ...
```

4. Login to ownCloud as the admin user. You might be asked for an upgrade, if the E2EE app was installed before.

Administration Setup

1. Open the Admin Settings and visit the



Encryption

section. Enter your license key in the provided text area:

License Key

[illegible]

Change license

Your license is active until May 7, 2020

For trial purposes e2ee includes a valid license for localhost. If you want to try it out on a real environment you can request a demo license by providing your owncloud url (before the index.php)

2. Select, which key storages will be available for your users. You may provide different settings for ownCloud and guest users.

Key Storage

Select below which private key storages are provided for e2ee Users.

ownCloud Users

- ☐ User's Computer/Device
- ☒ External Key/Smartcard
- ☒ Manual input for each download
- ☒ Local decryption, download only

Guest Users

- ☒ User's Computer/Device
- ☐ External Key/Smartcard
- ☒ Manual input for each download
- ☒ Local decryption, download only

If you provide more than one key storage options, users have to set up their key storage in their personal settings prior to being able to read and save encrypted files. This must be communicated in advance to avoid any confusion.

3. By default all users are enabled to use the E2ee app. If you want to restrict usage to specific groups only, you may set them in the *Authorized Groups* section. If you provide one or more groups here, only members of those groups may set a folder as E2ee encrypted. Click the apply button, when you are done.

Authorized Groups


✕ admin

By default all users are enabled to use the E2ee app.

If you provide one or more groups here, only members of those groups may set a folder as E2ee encrypted. (guests and E2EE enabled (virtual group) are virtual groups and cannot be selected).

Apply E2ee Groups

4. If you have the Guests app installed, make sure e2eeshare is added to the app whitelist. The Guests app is found in the



Sharing

section.

Guests

Guest users are grouped under a virtual group in the user manager

Group name

☒ Limit guest access to an app whitelist

settings,avatar,files_external,files_trashbin,files_versions,files_sharing,files_texteditor,activity,firstrunwizard,gallery,notifications,e2eeshare

Reset whitelist

FAQ

I got a valid license, but when installing it, I still get a message that the system is unlicensed.

This usually happens, when you did not specify correct URL(s) for your license keys. Make sure to send us the exact URL(s) the system will be visible from (i.e. <https://example.com/owncloud>) -> basically everything before `index.php`. If you plan to use different URLs for the same installation make sure to send us all of them.

Are there any file size limitations?

Short Answer: no

Long Answer: It depends on your browser, operating system and available RAM. Since the en-/decryption takes place in your browser the file needs to fit within the available memory. Depending on your configuration it should not be a problem sharing files > 2GB although the additional en-/decryption process might require you to wait for quite some time.

How long do you have to wait to have a file de-/encrypted?

De-/Encryption times for small files (<20MB) are barely noticeable on modern systems or even mobile devices. The larger the file gets the more noticeable is the wait after downloading (or before upload starts) - always depending on your hardware.